



Normal VWF Variation: The Moving Baseline

The laboratory value is measured once.
The patient has been changing for years.



The most common diagnostic error is treating a laboratory result as a permanent biological trait.



Assuming valid assay performance, none of these values are wrong. They all belong to the exact same person. Each describes the biology of a particular moment.

Every VWF value answers one of two distinct questions.



The Management Question

How much VWF is measurable today?

Focus:	The biological snapshot.
Clinical Use:	Immediate treatment, surgery, delivery planning, acute bleeding, or replacement monitoring.



The Diagnostic Question


Does today's value represent the patient's underlying hemostatic state?

Focus:	The underlying trajectory.
Clinical Use:	Evaluating lifetime baseline health, requiring integration of bleeding phenotype, family history, and sampling circumstances.

Takeaway: Interpretation begins by knowing which question is being asked.

The baseline is not a fixed point. **It is a shifting trajectory.**

VWF is **exquisitely sensitive to physiologic state, age, endothelial activation, and clearance**. Its circulating level is a dynamic interaction of synthesis and clearance, not a static number.




Baseline is a physiologic range that shifts across the life course.

The changing nature of VWF is driven by three distinct movements.



Pillar 1: Biology Moves

Internal mechanisms, acute-phase reactions, and hormonal shifts alter measurable VWF.



Pillar 2: The Patient Moves


The patient progresses through different biological and clinical life stages, changing the context of the sample.




Pillar 3: Interpretation Moves

Clinical meaning shifts based on guidelines, assay methods, and diagnostic thresholds.

Movement 1: Biology acts as an acute-phase reactant.




Crucial Insight: If VWF is already low during an acute-phase state, the patient's unstressed baseline is likely even lower.



The Floor (Stable Determinants):
ABO blood group modifies the baseline level. Group O individuals clear VWF more rapidly, resulting in lower average levels.

Clinical Rule: ABO modifies the level, but it does not replace clinical interpretation. **Do not dismiss a low VWF value in a bleeding patient merely because they have Type O blood.**

Movement 2: The patient changes even when the inherited diagnosis does not.



Takeaway: The circumstance entirely changes the meaning of the sample.
The direction of change is not always predictable.

Movement 3: Interpretation requires context, not just a threshold.

**45
IU/dL**

The 2021 Guideline Lens

Node 1: Bleeding History

Under 2021 guidelines, <50 IU/dL with abnormal bleeding supports Type 1 VWD.

Node 2: Absolute Threshold


A level <30 IU/dL supports the diagnosis regardless of bleeding history.

Node 3: Historical Terminology


Values between 30 and 50 IU/dL may carry the historical label "low VWF" depending on the institution.

Key Insight: A value of 45 IU/dL has vastly different implications if obtained during baseline health versus during resolution of an inflammatory illness. The number is the same; the meaning is not.


Has the biology moved, or has the measurement system?



Best Practices for Serial Comparison:

	1. Ensure appropriately handled samples.		2. Document the patient's physiologic state.		3. Use the same or analytically comparable assays.		4. Interpret antigen, activity, and FVIII relationally, not independently.
---	--	--	--	---	--	---	--

Repeat testing is an act of interpretation, not mere repetition.



The Myth:

Repeating a test automatically reveals the single "true" value.

The Reality:

Statistical variation means an unusually low or high result will often move closer to the patient's usual range when repeated.


Why we repeat tests:




To evaluate transient physiologic elevations.



To confirm persistent quantitative deficiency.



To clarify borderline results near a diagnostic threshold.




To investigate discordance between phenotype and initial labs.

Takeaway: Repeat testing provides additional observations to infer a more credible biological range.

The Extremes: How Aging and Pregnancy shift the baseline.


Aging (The Decades-Long Shift)



VWF commonly increases with age, moving historical Type 1 VWD patients into “normal” lab ranges.

Warning: Laboratory normalization does not by itself establish that the bleeding risk has resolved.

Pregnancy (The 9-Month Spike)




VWF and FVIII rise substantially during gestation, improving hemostatic reserve.

Warning: Great for delivery management, but unrepresentative of baseline biology. After delivery, VWF falls rapidly, contributing to postpartum bleeding risk.


When the laboratory and the patient disagree.

Discordance is not diagnostic failure. It is diagnostic information.



Takeaway: The goal is not to decide whether the laboratory or the patient is "right," but to determine why they appear to disagree.

The Synthesis: The 46 IU/dL Paradox



Patient A: 19-year-old, baseline health, lifelong bleeding.

Interpretation: VWF <50 IU/dL with abnormal bleeding supports Type 1 VWD. The 46 represents their true baseline.

Patient B: 72-year-old recovering from pneumonia. Historical VWF of 28 IU/dL.

Interpretation: Age and acute illness (pneumonia) have raised the value to 46. The historical 28 is the true baseline.

The Reveal: The laboratory values are identical. The biological trajectory and clinical meaning are completely different.

Guideline Integration & Best Practices.



Test during baseline health:

Avoid testing during acute bleeding, infection, or major stress for diagnostic purposes.



Relational Interpretation:

Interpret Antigen, Activity, and FVIII together, not as isolated numbers.



Contextualize Blood Type:

Do not use ABO Blood Group O alone to dismiss a low VWF result in a symptomatic patient.




Integrate Phenotype:

A normalized lab value (e.g., due to aging) does not automatically erase a previously sound diagnosis or bleeding history.

The Golden Rule: Before interpreting a VWF value, ask why it was measured, what assay was used, and the patient's state of health at the time of the draw.

The baseline itself moves.



Diagnosis begins with measurement.
Interpretation begins with context.

The laboratory value is measured once. The patient has been changing for years.